



Tectonics

Supporting Information for

Kinematics of foreland-vergent crustal accretion: inferences from the Dinarides evolution

Marianne van Unen^{1,2}, Liviu Matenco², Fadi Henri Nader¹, Romain Darnault¹, Oleg Mandic³ and Vedad Demir⁴

¹IFP Energies Nouvelles, Rueil-Malmaison, France, ²Utrecht University, Faculty of Geosciences, Utrecht, The Netherlands, ³Natural History Museum Vienna, Vienna, Austria, ⁴Federal Institute for Geology, Sarajevo, Bosnia-Herzegovina.

Contents of this file

Tables S1 to S18

Introduction

This supporting information provides the kinematic data of measured fault and folds and their associated kinematic sense of shear, measured in a surface field study. The paleostress axes (PBT-axes, and Shmin and Shmax) for this data have been obtained by the use of the Wintensor software.

Table S1. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the Bosnian Flysch zone and the Sarajevo-Zenica Basin. For the stereoplots associated with this data see Figure 4b. I= inverse. Dir= direction, azim=azimuth, incl=inclination. The compressional (P-axes), intermediate (B-axes) and tensional (T-axes) stress for each fault set are calculated by the use of the PBT method (Delvaux & Sperner, 2003). Shmax and Shmin are the horizontal stress axes.

Table S2. Kinematic data derived during this field study and paleostress data derived by the use of WinTensor for the area of the Bosnian Flysch zone and the Sarajevo-Zenica Basin. For the stereoplots associated with this data see Figure 4c. I= inverse. Further table conventions as in table S1.

Table S3. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the Bosnian Flysch zone and the Sarajevo-Zenica Basin. For the stereoplots associated with this data see Figure 4d. N= Normal. Further table conventions as in table S1.

Table S4. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the Bosnian Flysch zone and the Sarajevo-Zenica Basin. For the stereoplots associated with this data see Figure 4e. D= dextral, S= sinistral. Further table conventions as in table S1.

Table S5. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the Bosnian Flysch zone and the Sarajevo-Zenica Basin. For the stereoplots associated with this data see Figure 4f. I=inverse. Further table conventions as in table S1.

Table S6. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the Lower Neretva River Valley. For the stereoplots associated with this data see Figure 6b. I= inverse. Further table conventions as in table S1.

Table S7. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the Lower Neretva River Valley. For the stereoplots associated with this data see Figure 6c. N= normal. Further table conventions as in table S1.

Table S8. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the Lower Neretva River Valley. For the stereoplots associated with this data see Figure 6d. D= dextral, S= sinistral. Further table conventions as in table S1.

Table S9. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the Lower Neretva River Valley. For the stereoplots associated with this data see Figure 6e. I=inverse. Further table conventions as in table S1.

Table S10. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the Durmitor Flysch zone of Montenegro. For the stereoplots associated with this data see Figure 8b. I= inverse. Further table conventions as in table S1.

Table S11. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the Durmitor Flysch zone of Montenegro. For the stereoplots associated with this data see Figure 8c. N=normal. Strike and Dip+dir measurements are taken from Dohmen (2012). Further table conventions as in table S1.

Table S12. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the Durmitor Flysch zone of Montenegro. For the stereoplots associated with this data see Figure 8d. D= dextral, S= sinistral.. Further table conventions as in table S1.

Table S13. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the area of coastal Montenegro. For the stereoplots associated with this data see Figure 9b. N=normal. Further table conventions as in table S1.

Table S14. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the area of coastal Montenegro. For the stereoplots associated with this data see Figure 9c. I=inverse. Further table conventions as in table S1.

Table S15. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the area of coastal Montenegro. For the stereoplots associated with this data see Figure 9d. I=inverse. Further table conventions as in table S1.

Table S16. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the area of coastal Montenegro. For the stereoplots associated with this data see Figure 9e. N=normal. Further table conventions as in table S1.

Table S17. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the area of coastal Montenegro. For the stereoplots associated with this data see Figure 9f. D=dextral, S=sinistral. Further table conventions as in table S1.

Table S18. Kinematic data derived during this field study and paleostress data obtained by the use of WinTensor for the area of the area of coastal Montenegro. For the stereoplots associated with this data see Figure 9g. I=inverse. Further table conventions as in table S1.

Kinematic field data					P-axes	B-axes	T-axes	Shmax	Shmin
id	type	dip-dir/dip	Azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fault	143/25	143/25		323/20	53/0	143/70	143	53
2	Fault	300/40	300/40		120/5	210/0	300/85	120	30
3	Fault	302/37	302/37		122/8	32/0	302/82	122	32
4	Fold		032/33						
5	Fold		043/24						
6	Fold		050/40						
7	Fold		026/13						
8	Fold		040/12						

Kinematic field data					P-axes	B-axes	T-axes	Shmax	Shmin
id	type	dip-dir/dip	Azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fault	233/51	233/51	N	53/84	323/00	233/6	143	053
2	Fault	213/79	213/79	N	33/56	303/00	213/34	123	033
3	Fault	015/67	015/67	N	195/68	285	15/22	105	015
4	Fault	102/70	102/70	N	182/65	12	102/25	012	102
5	Fault	100/60	100/60	N	280/75	10	100/15	010	100
6	Fault	250/60	268/58	N	46/72	165/8	257/14	170	080
7	Fault	144/60	144/60	N	324/75	54/00	144/15	054	144
8	Fault	142/70	142/70	N	322/65	52/00	142/25	052	142
9	Fault	210/70	210/70	N	30/65	120/00	210/25	120	030
10	Fault	20/65	20/65	N	200/70	290/00	020/20	110	020
11	Fault	182/75	207/73	N	352/59	94/7	188/29	106	016
12	Fault	010/75	010/75	N	190/60	280/00	010/30	100	010
13	Fault	213/75	223/75	N	29/60	124/02	215/30	128	038
14	Fault	060/62	060/62	N	240/73	330/00	060/17	150	060
15	Fault	040/80	040/80	N	220/55	130/00	040/35	130	040
16	Fault	252/62	262/62	N	61/73	164/04	255/17	166	076
17	Fault	320/70	254/48	N	182/50	35/35	293/16	016	106
18	Fault	302/37	302/37	N	302/82	32/00	122/08	032	122
19	Fault	217/68	217/68	N	37/67	307/00	217/23	127	037
20	Fault	171/75	219/68	N	330/57	85/16	184/28	105	015

Kinematic field data					P-axes	B-axes	T-axes	Shmax	Shmin
	type	dip-dir/dip	Azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fault	191/42	191/42		11/03	101/00	191/87	011	101
2	Fault	50/27	50/27		230/18	320/00	50/72	50	140
3	Fault	31/20	31/20		211/25	121/00	31/65	31	121
4	Fault	26/34	26/34		206/11	116/00	26/79	26	116
5	Fault	236/47	236/47		236/02	146/00	56/88	56	146
6	Fault	237/34	237/34		057/11	327/00	237/79	57	147
7	Fault	30/25	030/25		210/20	120/00	30/70	30	120
8	Fault	054/30	024/27		215/17	121/13	355/68	39	129
9	Fault	53/42	053/42		233/03	143/00	53/87	53	143
10	Fault	058/50	032/46		046/03	136/13	303/76	45	135
11	Fault	066/30	044/29		232/16	139/9	19/72	55	145
12	Fault	210/25	230/24		044/21	137/8	246/68	40	130
13	Fault	038/28	38/28		218/17	128/00	38/73	38	128
14	Fold		305/19						
15	Fold		133/11						
16	Fold		300/10						
17	Fold		300/8						
18	Fold		336/15						
19	Fold		338/21						
20	Fold		328/8						
21	Fold		137/8						
22	Fold		315/18						
23	Fold		316/33						
24	Fold		300/35						
25	Fold		294/18						
26	Fold		344/26						
27	Fold		335/10						
28	Fold		134/8						
29	Fold		320/5						
30	Fold		349/35						
31	Fold		120/10						
32	Fold		134/22						
33	Fold		316/30						
34	Fold		340/04						
35	Fold		328/04						

Kinematic field data				P-axes	B-axes	T-axes	Shmax	Shmin	
id	type	dip-dir/dip	Azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fault	17/82	105/10	D	136/13	325/77	226/02	136	046
2	Fault	239/51	169/22	D	190/1	281/43	100/47	010	100
3	Fault	253/84	342/09	D	12/11	196/79	103/01	012	102
4	Fault	116/74	43/45	S	359/49	192/41	096/06	004	094
5	Fault	50/54	334/19	D	177/1	86/48	268/42	177	087
6	Fault	172/72	254/24	S	225/11	115/59	321/28	048	138
7	Fault	032/85	303/20	D	334/15	109/69	240/14	152	062
8	Fault	346/78	257/06	S	227/11	13/77	136/07	046	136
9	Fault	320/70	249/42	S	207/49	31/41	299/02	028	118
10	Fault	264/83	179/38	D	213/28	345/51	109/24	026	116
11	Fault	060/80	336/30	D	007/20	134/58	268/24	002	092
12	Fault	076/89	347/18	D	18/15	163/72	285/10	017	107
13	Fault	306/65	223/15	S	193/26	341/60	096/14	009	099
14	Fault	088/62	170/13	D	199/25	58/58	298/17	023	113

Kinematic field data					P-axes	B-axes	T-axes	Shmax	Shmin
id	type	dip-dir/dip	Azim/plunge	sense	Azim/incl	Azim/incl	Azimuth/incl	azim	azim
1	Fault	195/44	191/44		13/01	283/02	129/88	013	103
2	Fault	185/42	185/42		005/3	275/00	185/87	005	095
3	Fault	175/65	175/65		175/20	265/00	355/70	175	085
4	Fold		087/18						
5	Fold		096/26						
6	Fault	004/45	004/45		004/00	94/00	184/90	004	094
7	Fold		284/25						
8	Fault	044/52	011/47		029/5	120/17	284/72	028	118
9	Fold		100/04						
10	Fold		274/05						
11	Fold		270/30						
12	Fold		286/62						
13	Fault	358/47	358/47		358/02	88/00	178/88	178	088
14	Fault	040/70	006/66		030/24	125/12	241/63	023	113
15	Fold		083/16						

Kinematic field data					P-axes	B-axes	T-axes	Shmax	Shmin
id	type	dip-dir/dip	azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fault	33/32	33/32	I	213/13	303/00	033/77	033	123
2	Fault	40/25	40/25	I	220/20	310/00	040/70	040	130
3	Fault	235/52	235/52	I	235/7	325/00	055/83	055	145
4	Fault	23/70	23/70	I	023/25	293/00	203/65	023	113
5	Fault	62/24	62/24	I	242/21	152/00	062/69	062	152
6	Fault	34/34	34/34	I	214/11	124/00	34/79	034	124
7	Fault	72/41	72/41	I	252/04	162/00	72/86	072	162
8	Fault	240/37	246/37	I	063/08	154/03	263/81	063	153
9	Fault	070/45	070/45	I	070/00	160/00	250/90	070	160
10	Fault	045/62	61/61	I	051/17	319/07	207/72	054	144
11	Fault	040/50	040/50	I	040/05	130/00	220/85	040	130
12	Fault	070/30	079/30	I	256/15	347/04	091/74	075	165
13	Fault	210/65	210/65	I	210/20	120/00	030/70	030	120
14	Fault	195/33	195/33	I	015/12	285/00	195/78	015	105
15	Fault	35/48	35/48	I	035/03	125/00	215/87	035	125
16	Fault	032/52	032/52	I	032/07	302/00	212/83	032	122
17	Fault	028/46	028/46	I	028/01	118/00	208/89	028	118

Kinematic field data					P-axes	B-axes	T-axes	Shmax	Shmin
id	type	dip-dir/dip	azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fault	58/30	48/30	N	035/75	140/04	232/15	143	53
2	Fault	140/82	210/68	N	298/49	53/20	157/34	085	175
3	Fault	275/72	291/71	N	087/63	187/05	279/27	013	103
4	Fault	284/60	317/55	N	065/69	203/16	297/13	031	121
5	Fault	264/58	268/58	N	077/77	175/02	266/13	176	86
6	Fault	285/14	284/14	N	284/59	14/00	104/31	014	104
7	Fault	357/66	016/65	N	162/68	270/07	003/21	096	6
8	Fault	340/65	340/65	N	160/70	70/00	340/20	070	160
9	Fault	65/46	030/40	N	323/71	136/18	227/02	138	48
10	Fault	340/45	323/44	N	245/82	61/09	151/01	061	151
11	Fault	68/65	136/39	N	198/48	002/41	099/08	012	102
12	Fault	86/50	086/50	N	266/85	176/00	086/05	176	86
13	Fault	76/43	76/43	N	017/88	163/03	253/02	163	73
14	Fault	263/52	263/52	N	083/83	173/173	263/07	173	83
15	Fault	043/63	043/63	N	223/72	313/00	043/18	133	43
16	Fault	110/85	110/85	N	290/50	200/00	110/40	20	110
17	Fault	33/66	88/52	N	171/58	316/27	055/16	150	60
18	Fault	131/51	138/51	N	284/84	044/03	134/06	44	134
19	Fault	148/53	148/53	N	328/82	238/00	148/8	58	148
20	Fault	100/62	108/62	N	271/73	012/03	103/17	14	104
21	Fault	225/41	225/41	N	225/86	135/00	045/04	135	45
22	Fault	195/61	171/59	N	042/72	279/11	186/15	93	3
23	Fault	50/65	50/65	N	230/70	140/00	050/20	140	50
24	Fault	207/51	207/51	N	027/84	117/00	207/06	117	27
25	Fault	032/63	032/63	N	212/72	122/00	032/18	122	32
26	Fault	54/54	54/54	N	234/81	324/00	054/09	144	54
27	Fault	238/85	238/85	N	058/50	148/00	238/40	148	58
28	Fault	56/75	56/75	N	236/60	326/00	056/30	146	56
29	Fault	280/48	280/48	N	100/87	190/00	280/03	10	100
30	Fault	240/72	240/72	N	060/63	150/00	240/27	150	60
31	Fault	50/85	50/85	N	230/50	140/00	050/40	140	50
32	Fault	98/74	98/74	N	278/61	008/00	098/29	8	98
33	Fault	70/65	70/65	N	250/70	160/00	070/20	160	70
34	Fault	131/40	131/40	N	131/85	41/00	311/05	41	131
35	Fault	238/65	238/65	N	058/70	148/00	238/20	148	58
36	Fault	285/25	285/25	N	285/70	195/00	105/20	15	105
37	Fault	252/67	252/67	N	072/68	162/00	252/22	162	72
38	Fault	45/55	45/55	N	225/80	315/00	045/10	135	045

Kinematic field data						P-axes	B-axes	T-axes	Shmax	Shmin
id	type	dip-dir/dip	azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim	
1	Fault	82/62	161/20	D	192/32	40/55	290/14	40	14	
2	Fault	310/86	222/15	S	175/13	26/74	267/08	26	8	
3	Fault	126/75	205/36	S	161/13	55/50	262/37	55	37	
4	Fault	27/68	107/23	D	157/33	336/57	067/01	336	1	
5	Fault	190/82	103/21	D	148/09	260/67	055/21	260	21	
6	Fault	185/68	185/11	D	316/24	155/65	049/07	155	7	
7	Fault	351/46	288/25	D	135/11	37/36	240/52	37	52	
8	Fault	34/40	308/03	D	160/30	41/40	274/35	41	35	
9	Fault	80/72	161/25	S	119/05	22/58	212/31	22	31	
10	Fault	238/89	148/09	D	193/06	322/81	103/07	322	7	
11	Fault	56/80	328/09	D	192/01	99/76	282/14	99	14	
12	Fault	84/80	358/20	D	042/07	149/67	310/21	149	21	
13	Fault	88/65	003/10	D	223/10	113/63	318/25	113	25	
14	Fault	334/60	247/05	S	205/25	346/59	107/17	346	17	
15	Fault	86/73	176/03	D	220/14	76/73	312/10	76	10	
16	Fault	306/80	219/16	S	172/19	005/71	263/04	5	4	
17	Fault	17/85	105/20	D	153/18	300/69	059/10	300	10	
18	Fault	200/78	111/05	D	335/05	223/77	066/12	223	12	
19	Fault	87/78	358/06	D	222/04	114/77	313/13	114	13	
20	Fault	239/79	327/08	D	013/13	202/76	103/02	202	2	
21	Fault	288/78	199/06	S	154/13	315/77	063/04	315	4	
22	Fault	355/60	066/29	S	211/01	301/46	120/44	301	44	
23	Fault	222/86	312/05	D	357/06	171/84	267/01	171	1	
24	Fault	96/85	008/19	S	320/17	172/70	053/10	172	10	
25	Fault	98/74	188/03	S	324/09	88/74	088/13	88	13	
26	Fault	87/78	358/06	S	313/13	114/77	114/04	114	4	
27	Fault	239/79	327/08	D	013/13	202/76	103/02	202	2	
28	Fault	288/78	199/06	S	154/13	315/77	063/04	315	4	
29	Fault	105/59	189/10	S	331/14	83/57	233/29	83	29	
30	Fault	76/55	002/21	D	216/09	117/47	314/41	117	41	
31	Fault	007/69	290/31	D	330/06	68/51	235/38	68	38	
32	Fault	078/60	143/37	D	204/51	16/39	109/04	16	4	
33	Fault	062/88	332/09	D	017/05	140/81	287/08	140	8	
34	Fault	273/72	185/05	D	048/09	290/71	140/16	290	16	
35	Fault	137/87	048/22	S	001/18	220/68	220/13	220	13	

Kinematic field data					P-axes	B-axes	T-axes	Shmax	Shmin
id	type	dip-dir/dip	azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fault	160/81	184/80		164/36	71/04	335/54	173	83
2	Fault	170/81	180/80		171/36	80/02	348/54	174	84
3	Fault	187/30	187/30		007/15	97/00	187/75	7	97
4	Fault	190/70	190/70		190/25	280/00	010/65	10	100
5	Fault	198/72	198/72		198/27	288/00	018/63	18	108
6	Fault	171/75	161/75		169/30	260/02	355/60	166	76
7	Fault	181/33	181/33		001/12	271/00	181/78	1	91
8	Fault	183/42	183/42		003/3	273/00	183/87	3	93
9	Fault	010/56	010/56		010/11	100/00	190/79	10	100
10	Fault	340/50	340/50		341/05	251/01	145/85	161	71
11	Fault	009/55	014/55		011/10	281/02	178/80	11	101
12	Fault	158/63	187/60		168/17	74/12	310/69	172	82
13	Fault	002/50	011/50		006/05	276/04	145/83	6	96
14	Fault	034/55	008/52		023/09	115/13	259/74	21	111
15	Fault	041/61	009/57		029/14	123/15	256/69	25	115

Kinematic field data				P-axes	B-axes	T-axes	Shmax	Shmin	
id	type	dip-dir/dip	Azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fold		320/16						
2	Fold		335/20						
3	Fold		290/30						
4	Fold		344/04						
5	Fold		335/20						
6	Fold		324/14						
7	Fold		284/38						
8	Fold		306/37						
9	Fold		329/23						
10	Fold		319/33						
11	Fold		128/15						
12	Fold		155/04						
13	Fold		134/35						
14	Fold		288/17						
15	Fold		329/30						
16	Fold		287/25						
17	Fold		154/20						
18	Fold		322/25						
19	Fold		111/21						
20	Fold		334/07						
21	Fold		114/10						
22	Fault	220/53	225/53		222/08	132/02	025/82	042	132
23	Fault	227/52	212/52		220/07	311/07	086/80	039	129
24	Fold		137/19						
25	Fold		115/14						
26	Fold		348/18						
27	Fold		312/11						
28	Fold		120/35						
29	Fold		134/33						
30	Fold		315/21						
31	Fold		325/11						
32	Fold		134/08						
33	Fold		130/15						
34	Fold		344/13						
35	Fold		336/15						
36	Fold		286/12						
37	Fault	55/54	074/52		063/08	332/09	194/78	064	154
38	Fault	68/70	046/69		062/25	155/07	260/64	057	147
39	Fault	60/28	060/28		240/17	150/00	060/73	060	150
40	Fault	46/29	030/28		216/17	124/07	012/72	038	128
41	Fault	26/49	018/49		022/04	113/04	247/84	022	112

Kinematic field data						P-axes	B-axes	T-axes	Shmax	Shmin
id	type	Strike or Dip-dir/dip	Dip+dir	Azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fault	107	67S	211/66	N	006/67	109/05	201/22	114	24
2	Fault	119	69N	082/57	N	173/58	309/24	048/20	145	55
3	Fault	89	70N	063/50	N	138/52	283/33	024/17	121	31
4	Fault	86	63S	220/55	N	316/64	97/21	193/15	108	18
5	Fault	106	71N	062/64	N	170/60	292/17	030/24	129	39
6	Fault	122	72N	051/71	N	203/63	304/06	037/27	131	41
7	Fault	165	34W	223/30	N	186/70	322/15	055/13	148	58
8	Fault	148	50W	261/48	N	358/79	158/12	249/04	160	70
9	Fault	170	45E	070/45	N	345/90	165/05	255/00	165	75
10	Fault	2	55E	080/54	N	299/78	178/06	087/10	176	86
11	Fault	179	50W	245/47	N	152/76	348/12	258/04	167	77
12	Fault	179	45E	34/30	N	342/59	144/30	238/08	151	61
13	Fault	171	43E	46/38	N	346/72	151/18	242/05	153	63
14	Fault	30	80S	54/66	N	324/50	206/21	102/31	176	86
15	Fault	41	45N	014/24	N	061/52	266/35	167/12	72	162
16	Fault	102	60N	59/50	N	044/64	297/24	032/11	125	35
17	Fault	120	65N	42/65	N	001/70	302/05	034/20	126	36
18	Fault	160	53S	225/50	N	022/75	330/13	239/07	148	58
19	Fault	47	42N	028/16	N	068/46	285/37	180/19	82	172
20	Fault	117	68N	017/68	N	214/67	116/03	024/23	112	22
21	Fault	130	70N	012/68	N	236/64	127/10	032/25	116	26
22	Fault	111	40N	037/39	N	085/81	301/08	210/06	119	29
23	Fault	151	41S	251/41	N	297/86	157/05	066/04	156	66
24	Fault	149	48S	240/48	N	050/87	149/00	239/03	149	59
25	Fault	120	70N	014/69	N	219/64	118/05	026/25	112	22
26	Fault	120	65N	089/48	N	164/56	316/31	055/13	149	59
27	Fault	289/45		235/30	N	183/59	344/30	079/08	172	82
28	Fault	218/75		258/71	N	022/58	131/12	228/29	148	58
29	Fault	204/64		190/63	N	037/70	291/06	199/19	106	16
30	Fault	234/74		252/73	N	046/61	145/05	238/29	153	63
31	Fault	043/70		68/68	N	208/64	316/09	050/24	146	56
32	Fault	274/46		223/33	N	168/61	333/28	066/06	158	68
33	Fault	220/24		196/22	N	179/66	290/09	023/22	118	28
34	Fault	71	52N	306/46	N	222/71	056/18	325/04	54	144
35	Fault	37	64N	281/61	N	152/68	032/11	298/18	24	114
36	Fault	40	62N	299/62	N	142/73	038/05	306/17	34	124
37	Fault	47	31N	319/31	N	322/76	228/01	138/14	48	138
38	Fault	49	60S	109/56	N	355/70	221/14	127/13	33	123
39	Fault	45	33N	305/33	N	288/78	38/05	129/12	40	130
40	Fault	120	50N	335/34	N	277/58	89/31	181/03	93	3
41	Fault	71	36S	149/35	N	122/78	243/06	334/10	65	155
42	Fault	177	72E	154/50	N	227/49	10/34	113/19	31	121
43	Fault	144	72S	160/41	N	098/43	306/44	202/14	107	17
44	Fault	156	54S	288/46	N	008/68	173/22	265/05	177	87
45	Fault	52	59S	116/56	N	357/72	225/12	132/13	39	129
46	Fault	112	66N	327/52	N	244/58	99/27	0/16	85	175
47	Fault	110	56N	329/43	N	257/61	89/28	356/05	84	174
48	Fault	104	67S	153/61	N	044/63	277/17	180/20	83	173
49	Fault	84	70S	175/70	N	353/65	84/00	174/25	84	174
50	Fault	347/48		327/46	N	236/79	68/10	337/02	67	157
51	Fault	185/76		141/71	N	022/57	272/13	174/30	73	163
52	Fault	124/60		136/59	N	288/74	37/05	128/15	40	130

Kinematic field data					P-axes	B-axes	T-axes	Shmax	Shmin
id	type	dip-dir/dip	Azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fault	270/85	358/21	D	046/18	193/68	312/11	44	134
2	Fault	124/76	036/10	S	350/17	161/73	260/03	170	80
3	Fault	077/65	152/29	D	206/40	21/50	114/03	24	114
4	Fault	349/75	069/34	S	025/12	279/52	124/35	28	118
5	Fault	355/77	270/20	S	221/24	54/66	313/05	42	132
6	Fault	082/73	001/28	D	043/07	144/57	309/32	41	131
7	Fault	348/78	075/16	S	031/03	293/70	122/20	32	122
8	Fault	101/60	018/12	S	333/30	127/57	236/12	149	59
9	Fault	358/75	274/20	S	225/25	54/65	317/03	46	136
10	Fault	270/85	358/21	D	046/18	193/68	312/11	44	134
11	Fault	097/83	017/54	S	010/41	182/35	69/29	147	57
12	Fault	296/60	219/21	S	070/37	338/52	76/06	167	77

Kinematic field data					P-axes	B-axes	T-axes	Shmax	Shmin
id	type	Dip-dir/dip	azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fault	230/22	230/22	N	230/67	140/00	50/23	140	50
2	Fault	28/65	28/65	N	208/70	118/00	28/20	118	28
3	Fault	18/62	18/62	N	198/73	288/00	18/17	108	18
4	Fault	52/60	52/60	N	232/75	142/00	52/15	142	52
5	Fault	80/40	80/40	N	80/85	170/00	260/05	170	80
6	Fault	34/80	34/80	N	214/55	124/00	34/35	124	34
7	Fault	20/60	20/60	N	200/75	290/00	20/15	110	20
8	Fault	30/60	30/60	N	210/75	300/00	30/15	120	30
9	Fault	218/60	215/60	N	42/75	307/01	217/15	127	37
10	Fault	210/44	197/44	N	118/82	293/07	23/01	113	23
11	Fault	240/70	240/70	N	60/65	330/00	240/25	150	60
12	Fault	21/30	21/30	N	21/75	291/00	201/15	111	21
13	Fault	205/46	205/46	N	25/89	295/00	205/01	115	25
14	Fault	051/61	013/55	N	271/67	131/18	36/14	122	32

Kinematic field data					P-axes	B-axes	T-axes	Shmax	Shmin
id	type	dip-dir/dip	azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fault	314/55	314/55		314/10	44/00	134/80	134	44
2	Fault	290/31	290/31		110/14	20/00	290/76	110	20
3	Fault	113/20	113/20		293/25	23/00	113/65	113	23
4	Fault	344/27	344/27		164/18	74/00	344/72	164	74
5	Fault	300/41	300/41		120/04	210/00	300/86	120	30
6	Fold		38/30						
7	Fold		64/39						
8	Fault	134/46	134/46		134/01	44/00	314/89	134	44
9	Fault	127/53	127/53		127/08	217/00	307/82	127	37
10	Fault	112/49	112/49		112/04	22/00	292/86	112	22
11	Fault	146/47	163/46		154/02	64/09	254/81	154	64
12	Fault	107/25	107/25		287/20	17/00	107/70	107	17
13	Fold		206/10						
14	Fold		60/45						
15	Fold		59/46						
16	Fold		60/42						
17	Fold		70/30						
18	Fold		69/30						
19	Fold		40/02						
20	Fold		59/30						
21	Fold		235/26						
22	Fold		217/10						
23	Fold		79/30						
24	Fold		42/24						
25	Fold		44/50						
26	Fold		52/50						
27	Fold		61/28						
28	Fold		22/42						
29	Fold		66/46						
30	Fold		42/40						
31	Fold		38/15						
32	Fold		58/24						
33	Fold		64/40						
34	Fold		36/12						

Kinematic field data					P-axes	B-axes	T-axes	Shmax	Shmin
id	type	dip-dir/dip	azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fault	230/38	230/38		050/07	140/00	230/83	50	140
2	Fault	242/38	242/38		062/07	332/00	242/83	62	152
3	Fault	66/51	66/51		066/06	156/00	246/84	66	156
4	Fault	240/30	240/30		060/15	330/00	240/75	60	150
5	Fault	237/20	237/20		057/25	147/00	237/65	57	147
6	Fault	251/53	251/53		251/08	161/00	071/82	71	161
7	Fault	235/44	235/44		055/01	325/00	235/89	55	145
8	Fault	40/50	40/50		040/05	130/00	220/85	40	130
9	Fault	30/45	30/45		030/00	300/00	210/90	30	120
10	Fault	62/11	62/11		242/34	332/00	062/56	62	152
11	Fold		122/27						
12	Fold		122/15						
13	Fault	20/15	20/15		200/30	290/00	020/60	20	110
14	Fault	65/65	49/64		060/20	152/06	259/69	57	147
15	Fault	201/56	201/56		201/11	111/00	021/79	21	111
16	Fault	24/55	24/55		024/10	114/00	204/80	24	114
17	Fold		298/09						
18	Fold		326/18						
19	Fold		104/16						
20	Fold		308/15						
21	Fold		338/32						
22	Fold		118/28						
23	Fold		318/24						
24	Fold		155/38						
25	Fold		325/15						
26	Fold		130/28						
27	Fold		330/20						
28	Fold		154/15						
29	Fold		120/8						
30	Fold		328/22						
31	Fold		308/22						
32	Fold		352/25						
33	Fold		167/24						
34	Fold		151/21						
35	Fault	014/10	010/09		191/36	100/01	009/54	13	103
36	Fault	40/60	040/60		040/15	130/00	220/75	40	130
37	Fault	220/63	198/62		212/18	305/09	061/70	29	119
38	Fault	65/30	65/30		245/15	335/00	065/75	65	155
39	Fault	210/65	210/65		210/20	120/00	030/210	30	120
40	Fault	35/48	35/48		035/03	125/00	215/35	35	125

Kinematic field data					P-axes	B-axes	T-axes	Shmax	Shmin
id	type	dip-dir/dip	azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fault	228/62	175/48	N	96/59	301/28	205/11	111	21
2	Fault	272/65	210/45	N	139/53	343/34	245/12	151	61
3	Fault	004/58	38/53	N	140/70	285/17	018/11	111	21
4	Fault	260/22	231/19	N	215/62	324/10	059/25	156	66
5	Fault	134/32	134/32	N	134/77	224/00	314/13	44	134
6	Fault	170/40	166/40	N	146/85	258/02	348/05	78	168
7	Fault	63/61	63/61	N	243/74	333/00	063/16	153	63
8	Fault	52/49	52/49	N	232/86	322/00	052/04	142	52
9	Fault	290/60	290/60	N	110/75	200/00	290/15	20	110
10	Fault	21/30	21/30	N	21/75	291/00	201/15	111	21
11	Fault	183/24	198/23	N	209/67	106/06	013/22	100	10
12	Fault	42/40	042/40	N	42/85	132/00	222/05	132	42
13	Fault	64/51	64/51	N	244/84	334/00	064/6	154	64
14	Fault	215/40	215/40	N	215/85	305/00	035/05	125	35
15	Fault	210/47	210/47	N	30/88	120/00	210/02	120	30
16	Fault	200/45	200/45	N	200/90	110/00	020/00	110	20
17	Fault	250/75	208/70	N	88/58	337/13	239/29	139	49
18	Fault	245/60	287/52	N	20/66	168/21	262/12	176	86
19	Fault	284/40	284/40	N	284/85	194/00	104/05	14	104
20	Fault	51/61	013/55	N	271/67	131/18	036/14	122	32
21	Fault	147/80	162/80	N	324/55	57/03	149/35	64	154
22	Fault	112/49	112/49	N	292/86	22/00	112/04	22	112
23	Fault	260/54	216/44	N	140/65	331/24	239/04	148	58

Kinematic field data					P-axes	B-axes	T	Shmax	Shmin
id	type	dip-dir/dip	azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim
1	Fault	95/63	178/15	S	319/08	62/59	224/30	137	47
2	Fault	65/80	152/19	D	200/21	1/68	107/06	19	109
3	Fault	235/70	146/4	D	9/11	247/70	102/17	11	101
4	Fault	95/82	007/11	S	321/13	150/76	51/02	141	51
5	Fault	242/56	160/12	D	17/14	267/53	116/33	21	111
6	Fault	270/68	357/07	D	41/21	250/67	135/10	43	133
7	Fault	318/80	44/21	S	360/08	252/67	93/22	2	92
8	Fault	110/87	198/48	S	143/29	23/42	256/34	154	64
9	Fault	338/66	266/35	S	208/44	41/45	304/07	32	122
10	Fault	325/64	041/26	S	3/00	273/52	93/38	3	93
11	Fault	40/80	317/35	D	3/16	116/53	263/32	178	88
12	Fault	45/88	316/21	D	2/13	130/69	269/16	0	90
13	Fault	74/80	344/01	D	209/06	80/80	299/08	29	119
14	Fault	265/72	351/12	D	37/21	229/68	129/04	38	128
15	Fault	284/86	196/23	S	148/19	5/67	242/13	150	60
16	Fault	143/79	64/44	S	3/39	222/44	111/21	14	104
17	Fault	108/86	194/43	S	143/26	22/47	250/32	151	61
18	Fault	140/89	051/35	S	360/25	229/55	101/23	6	96
19	Fault	112/88	201/53	S	143/33	24/37	261/36	156	66

Kinematic field data						P-axes	B-axes	T-axes	Shmax	Shmin
id	type	dip-dir/dip	azim/plunge	sense	Azim/incl	Azim/incl	Azim/incl	azim	azim	
1	Fault	355/58	355/58		355/13	265/00	175/77	175	85	
2	Fault	215/75	170/70		204/29	301/14	53/57	13	103	
3	Fault	176/64	176/64		176/19	86/00	356/71	176	86	
4	Fault	010/60	010/60		10/15	280/00	190/75	10	100	
5	Fault	19/64	002/64		13/19	106/07	214/70	10	100	
6	Fault	178/62	178/62		178/17	88/00	358/73	178	88	
7	Fault	195/62	198/62		196/17	106/01	12/73	16	106	
8	Fault	210/65	189/63		203/19	296/08	49/69	20	110	
9	Fault	002/74	002/74		2/29	272/00	182/61	2	92	
10	Fault	175/70	175/70		175/25	85/00	355/65	175	85	
11	Fault	47/65	357/54		28/19	125/24	267/61	22	112	
12	Fault	44/55	009/50		29/08	121/18	276/71	27	117	
13	Fault	51/61	013/55		36/14	131/18	271/67	32	122	
14	Fault	175/80	162/80		173/35	265/02	358/55	168	78	
15	Fault	186/45	186/45		186/00	276/00	6/89	6	96	
16	Fault	145/63	169/61		153/17	60/10	301/70	156	66	
17	Fault	173/62	173/62		173/17	263/00	353/73	173	83	
18	Fault	200/62	189/62		196/17	288/05	32/72	14	104	
19	Fold		100/08							
20	Fold		092/05							
21	Fold		092/21							
22	Fold		085/28							
23	Fold		082/10							
24	Fold		260/18							
25	Fold		102/08							
26	Fold		280/24							
27	Fold		96/22							
28	Fold		94/12							
29	Fold		284/19							